

jamf | PRO

Jamf Pro Installation and Configuration Guide for Linux

Version 10.0.0



© copyright 2002-2017 Jamf. All rights reserved.

Jamf has made all efforts to ensure that this guide is accurate.

Jamf
100 Washington Ave S Suite 1100
Minneapolis, MN 55401-2155
(612) 605-6625

Under the copyright laws, this publication may not be copied, in whole or in part, without the written consent of Jamf.

Apache Tomcat and Tomcat are trademarks of the Apache Software Foundation.

Apple, Mac, macOS, OS X, and Safari are trademarks of Apple, Inc. registered in the U.S. and other countries.

The CASPER SUITE, COMPOSER®, the COMPOSER Logo®, Jamf, the Jamf Logo, JAMF SOFTWARE®, the JAMF SOFTWARE Logo®, RECON®, and the RECON Logo® are registered or common law trademarks of JAMF SOFTWARE, LLC in the U.S. and other countries.

Chrome is a trademark of Google, Inc.

Firefox is a registered trademark of the Mozilla Foundation.

Intel is a registered trademark of the Intel Corporation in the U.S. and other countries.

Linux is a registered trademark of Linus Torvalds in the United States and other countries.

Java and MySQL are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Microsoft and Windows are either registered trademarks or trademarks of Microsoft Corporation in the United States and other countries.

Red Hat and Red Hat Enterprise Linux are trademarks of Red Hat, Inc., registered in the United States and other countries.

Ubuntu is a registered trademark of Canonical Ltd.

All other product and service names mentioned herein are either registered trademarks or trademarks of their respective companies.

Contents

4 Preface

5 About This Guide

6 Additional Resources

8 Overview of Technologies

9 Applications and Utilities

10 Installed Files and Folders

11 Requirements

13 Installation

14 Installing Jamf Pro

17 Upgrading Jamf Pro

18 Setup

19 Setting Up Jamf Pro

20 Jamf Pro User Accounts and Groups

24 Activation Code

25 Integrating with an SMTP Server

27 Change Management

29 Integrating with GSX

32 Jamf Pro Summary

34 Server Infrastructure

35 About Distribution Points

38 File Share Distribution Points

40 Cloud Distribution Point

43 Jamf Distribution Server Instances

46 Jamf Infrastructure Manager Instances

48 Advanced Configuration

49 SSL Certificate

50 Configuring Tomcat to Work with a Load Balancer

51 Tomcat Thread Pool Settings

52 Jamf Pro Web App Memory

54 Viewing the Status of Database Tables

55 Clustering

57 Limited Access Settings

58 Backing Up the Database

63 Restoring Database Backups

65 Flushing Logs

67 Migrating to Another Server

jamf | PRO

Preface

About This Guide

The Jamf Pro server is a web app that functions as the administrative core of Jamf Pro. The Jamf Pro server allows you to perform inventory and remote management and configuration tasks on managed computers and mobile devices. All other administrative applications in Jamf Pro communicate with the Jamf Pro server.

This guide provides step-by-step instructions for installing and configuring Jamf Pro on the Linux platform. It also explains how to perform advanced configuration tasks.

Additional Resources

Jamf Nation

<https://www.jamf.com/jamf-nation/>

The Jamf Nation website allows you to communicate with other Jamf Pro administrators via discussions, submit feature requests, and access several different types of resources related to Jamf Pro.

Knowledge Base

<https://www.jamf.com/jamf-nation/articles>

The Knowledge Base contains hundreds of articles that address frequently asked questions and common issues.

Product Documentation

To access the following product documentation for a specific Jamf Pro version, log in to Jamf Nation and go to:

<https://www.jamf.com/jamf-nation/my/products>

- *Jamf Pro Release Notes*
The release notes include a list of new features, bug fixes, and known issues. They also explain how to upgrade Jamf Pro, and what you need to do to take advantage of new features.
- *Jamf Pro Administrator's Guide*
This guide contains overviews of features and instructions for performing administrative tasks using Jamf Pro.
- *Manually Installing Jamf Pro*
This technical paper explains how to manually install Jamf Pro on Linux and Windows platforms.
- QuickStart Guides
The *QuickStart Guide for Managing Computers* and the *QuickStart Guide for Managing Mobile Devices* serve as a starting point for new Jamf Pro administrators. They provide simplified workflows for performing basic administrative tasks, such as inventory and software distribution, and they reference related sections in the *Jamf Pro Administrator's Guide*.

In addition, you can search Jamf Nation to find technical documentation for other Jamf Pro apps, and technical papers that provide best-practice, step-by-step instructions on common workflows.

Other Resources

For access to other Jamf Pro-related resources, visit the following webpages:

- [Resources on jamf.com](#)
The Resources area on the Jamf website gives you access to product documentation, technical papers, and more.

- [Jamf 100 Course](#)

The Jamf 100 Course offers a self-paced introduction to Jamf Pro and an enterprise-focused foundation of the macOS, iOS, and tvOS platforms.

- [Jamf Knowledge Base Videos](#)

The Jamf YouTube channel features Knowledge Base videos and troubleshooting tips on managing computers and mobile devices with Jamf Pro.

jamf | PRO

Overview of Technologies

Applications and Utilities

This section provides an overview of the applications and utilities that you need to install and maintain Jamf Pro.

Jamf Pro Server

The Jamf Pro server (formerly the Jamf Software Server) is a web app that functions as the administrative core of Jamf Pro. The Jamf Pro server allows you to perform inventory and remote management and configuration tasks on managed computers and mobile devices. All other administrative applications in Jamf Pro communicate with the Jamf Pro server.

Jamf Pro Installer for Linux

The Jamf Pro Installer for Linux is a .run file that allows you to install and upgrade Jamf Pro on supported Linux operating systems.

To obtain the Jamf Pro Installer for Linux, log in to Jamf Nation and click **Show alternative downloads** below the Jamf Pro DMG on the following page:

<https://www.jamf.com/jamf-nation/my/products>

Jamf Pro Database Utility

The Jamf Pro database utility (formerly the JSS database utility) allows you to back up and restore the Jamf Pro database. It also allows you to restart Apache Tomcat and MySQL and modify their settings.

The Jamf Pro database utility is installed automatically when you run the Jamf Pro Installer. It is located in:

```
/usr/local/jss/bin/JSSDatabaseUtil.jar
```

Installed Files and Folders

The following files and folders are installed when you run the Jamf Pro Installer:

Jamf Pro web app

The files that make up the Jamf Pro web app (formerly the JSS web app) are stored in the following location:

```
/usr/local/jss/tomcat/webapps/ROOT/
```

Apache Tomcat

Tomcat is the web application server that runs the Jamf Pro web app. A directory named `tomcat` is installed in the following location:

```
/usr/local/jss/
```

For more information about the version of Tomcat installed by the Jamf Pro Installer, see the [Apache Tomcat Version Installed by the Jamf Pro Installer](#) Knowledge Base article.

jamf.tomcat8

This is the service file for Tomcat. It is installed in the following location:

```
/etc/init.d/jamf.tomcat8
```

server.xml

The Jamf Pro Installer installs a modified copy of Tomcat's `server.xml` file. This file enables SSL, ensures that Jamf Pro appears in the `root` context, and enables database connection pooling. It is installed in the following location:

```
/usr/local/jss/tomcat/conf/
```

keystore

Tomcat requires a `.keystore` file to provide connections over SSL. The Jamf Pro Installer creates a default `.keystore` file and stores it in the following location:

```
/usr/local/jss/tomcat/
```

Jamf Pro database utility

The Jamf Pro database utility (formerly the JSS database utility), filename `JSSDatabaseUtil.jar`, is installed in the following location:

```
/usr/local/jss/bin/
```

Database backup location

By default, the Jamf Pro database utility stores database backups in the following location:

```
/usr/local/jss/backups/database/
```

Logs

Logs for the installation and for the Jamf Pro server (formerly the Jamf Software Server) are stored in the following location:

```
/usr/local/jss/logs/
```

Requirements

This section lists the requirements for the applications and utilities you need to install and maintain Jamf Pro.

Jamf Pro Server

You can host Jamf Pro on any server that meets the following requirements:

- Java 1.8
- MySQL 5.6.x or 5.7.x (MySQL 5.7.x is recommended)
- Apache Tomcat 7 or 8.0.x (Tomcat 8.0.x is recommended)

Tested Linux operating systems include:

- Ubuntu 14.04 LTS Server
- Ubuntu 16.04 LTS Server
- Red Hat Enterprise Linux (RHEL) 6.8 and 7.3

Although you can install Jamf Pro on any server that meets the minimum requirements, the Jamf Pro Installer for Linux has additional requirements. (For more information, see the next section.)

Tested browsers for Jamf Pro are as follows:

- Safari
- Mozilla Firefox
- Google Chrome
- Microsoft Internet Explorer 10 or later

Jamf Pro Installer for Linux

The Jamf Pro Installer for Linux requires the following:

- Minimum operating systems:
 - Ubuntu 12.04 LTS Server (64-bit)
 - Red Hat Enterprise Linux (RHEL) 6.4, 6.5, 6.6, or 7.0
- Recommended operating systems:
 - Ubuntu 14.04 LTS Server (64-bit)
 - Ubuntu 16.04 LTS Server (64-bit)
 - Red Hat Enterprise Linux (RHEL) 6.8
 - Red Hat Enterprise Linux (RHEL) 7.3

In addition, you need the following:

- A 64-bit capable Intel processor

- 2 GB of RAM
- 400 MB of disk space available
- One of the following operating systems:
 - Ubuntu 12.04 LTS Server (64-bit)
 - Ubuntu 14.04 LTS Server (64-bit)
 - Red Hat Enterprise Linux (RHEL) 6.4, 6.5, 6.6, or 7.0
- Open Java Development Kit (OpenJDK) 8
For installation instructions, go to <http://openjdk.java.net/install/>.
- MySQL 5.6.x or 5.7.x (MySQL 5.7.x is recommended)
You can download MySQL from:
<https://www.mysql.com/downloads/>
- Wget utility installed
- Ports 8443 and 8080 available

Jamf Pro Database Utility

The Jamf Pro database utility (formerly the JSS database utility) requires a server with MySQL 5.6.x or 5.7.x (MySQL 5.7.x is recommended) installed.

jamf | PRO

Installation

Installing Jamf Pro

Installing Jamf Pro involves the following steps:

1. Install the required software (if you haven't already).
2. Create the Jamf Pro database.
3. Run the Jamf Pro Installer.

Before you begin, make sure your server meets the Jamf Pro Installer requirements. (For more information, see [Requirements](#).)

Note: For instructions on how to manually install Jamf Pro on Linux, see the [Manually Installing Jamf Pro](#) technical paper.

Step 1: Install the Required Software

Java and MySQL must be installed on the server before you can create the Jamf Pro database and run the Jamf Pro Installer. For instructions on how to install and configure Java and MySQL, see the following Knowledge Base article:

[Installing Java and MySQL](#)

Step 2: Create the Jamf Pro Database

Create a MySQL database in which Jamf Pro can store its data and a MySQL user that can access the database.

A default MySQL database name, username, and password are used throughout the instructions in this section. It is recommended, however, that you use a custom username and password that comply with your organization's security requirements. It is also recommended that you not use "root" as the username. A different database name can also be set if desired.

The default MySQL settings used in the instructions below are:

- Database name: jamfsoftware
- Username: jamfsoftware
- Password: jamfsw03

Note: If you customize any of the MySQL settings, you will be prompted to enter them on the Database pane when you run the Jamf Pro Installer.

1. Open a command prompt and access the MySQL command line as "root" by typing something similar to the following:

```
mysql -u root -p
```

If you did not create a root password when installing MySQL, do not type `-p`.

If MySQL is not in the path or it is installed in a custom location, enter the installation path in place of `mysql`.

2. If prompted, enter the password for the MySQL "root" user.
3. Create a database by executing:

```
CREATE DATABASE jamfsoftware;
```

You can customize the database name by replacing `jamfsoftware` with the desired name as shown in the following example:

```
CREATE DATABASE myDatabaseName;
```

4. Create a new MySQL user:

```
CREATE USER 'jamfsoftware'@'localhost' IDENTIFIED BY 'jamfsw03';
```

5. Grant access to that user so that it can access the database:

```
GRANT ALL ON jamfsoftware.* TO 'jamfsoftware'@'localhost';
```

You can customize the MySQL username and password by replacing `'jamfsoftware'` and `'jamfsw03'` with the desired username and password as shown in the following examples:

```
CREATE USER 'customUsername'@'localhost' IDENTIFIED BY  
'customPassword';
```

```
GRANT ALL ON myDatabaseName.* TO 'customUsername'@'localhost';
```

Step 3: Run the Jamf Pro Installer

The Jamf Pro Installer for Linux installs Apache Tomcat and the Jamf Pro web app.

1. Copy the Jamf Pro Installer for Linux (`jamfproinstaller.run`) to the server.
Note: To obtain the Jamf Pro Installer for Linux, log in to Jamf Nation and click **Show alternative downloads** below the Jamf Pro DMG on the following page:
<https://www.jamf.com/jamf-nation/my/products>
2. Log in to the server as a user with superuser privileges.

3. Initiate the installer by executing a command similar to the following:

```
sudo sh /path/to/jamfproinstaller.run
```

4. When the requirement check is complete, type "y" to proceed.
5. (RHEL only) When the installation is complete, edit the firewall configuration to allow access to port 8443 by executing:

```
sudo system-config-firewall-tui
```

6. (RHEL only) Choose **Other** or **Customize**, and manually add port 8443 with TCP protocol. The option you choose depends on whether you have a GUI or shell-only interface.
7. Access Jamf Pro by opening a web browser and typing the protocol, IP address or hostname of the server, and port. For example:
`https://jss.mycompany.com:8443/`
8. If you entered a custom database name, username, or password when you created the Jamf Pro database, or MySQL is using a port other than 3306, the Database Connection Properties pane is displayed. Before you can access Jamf Pro, you must follow the onscreen instructions to create a connection between the Jamf Pro server and the database.

Related Information

For related information, see the following section in this guide:

[Installed Files and Folders](#)

Learn about the files and folders that are installed by the Jamf Pro Installer.

For related information, see the following Knowledge Base article:

[Apache Tomcat Version Installed by the Jamf Pro Installer](#)

View the Tomcat version that is installed by the Jamf Pro Installer.

Upgrading Jamf Pro

This section explains how to upgrade Jamf Pro.

Note: To take full advantage of all new features, bug fixes, and enhancements, it is recommended that you use the latest version of Jamf Pro and the Jamf Pro apps. To upgrade the Jamf Pro apps, simply replace the existing apps with the latest version.

1. Back up the current database using the Jamf Pro database utility.
For more information, see [Backing Up the Database](#).
2. Copy the latest version of the Jamf Pro Installer for Linux (`jamfproinstaller.run`) to the server.
Note: To obtain the Jamf Pro Installer for Linux, log in to Jamf Nation and click **Show alternative downloads** below the Jamf Pro DMG on the following page:
<https://www.jamf.com/jamf-nation/my/products>
Note: The Jamf Pro Installer for Linux cannot be used to upgrade Jamf Pro 8.1 or earlier.
3. Log in to the server as a user with superuser privileges.
4. Initiate the installer by executing:

```
sudo sh /path/to/ jamfproinstaller.run
```

5. Follow the onscreen instructions to complete the upgrade.

jamf | PRO

Setup

Setting Up Jamf Pro

The first time you connect to the Jamf Pro server, the Jamf Pro Setup Assistant guides you through the following setup tasks:

- Accept the license agreement.
- Enter your activation code.
- Create your first Jamf Pro user account.
- Enter your Jamf Pro URL (formerly the JSS URL).
The Jamf Pro URL is the URL that client applications, computers, and mobile devices will connect to when communicating with the Jamf Pro server.

After you complete the Jamf Pro Setup Assistant, you can click the setup tips that are displayed onscreen to start configuring commonly used settings.

You may also want to make changes to the following pre-configured settings to ensure they meet the needs of your organization. These settings are important because over time, they can significantly affect the size of your database and your levels of network traffic:

- **“Update Inventory” policy**—Determines how often computers submit inventory to Jamf Pro. For more information, see "Computer Inventory Collection" in the *Jamf Pro Administrator's Guide*.
- **Recurring check-in frequency**—Determines the interval at which computers check in with Jamf Pro for available policies. For more information, see "Recurring Check-in Frequency" in the *Jamf Pro Administrator's Guide*.
- **Mobile device inventory collection frequency**—Determines how often mobile devices submit inventory to Jamf Pro. For more information, see "Mobile Device Inventory Collection Settings" in the *Jamf Pro Administrator's Guide*.

Related Information

For related information, see the following Knowledge Base article:

[Network Ports Used by Jamf Pro](#)

Learn about the network ports that you may need to configure when setting up Jamf Pro.

Jamf Pro User Accounts and Groups

Jamf Pro is a multi-user application. Jamf Pro user accounts and groups allow you to grant different privileges and levels of access to each user.

When configuring a Jamf Pro user account or group, you can grant access to the full Jamf Pro or to a specific site. You can grant privileges by choosing one of the following privilege sets:

- **Administrator**—Grants all privileges.
- **Auditor**—Grants all read privileges.
- **Enrollment Only**—Grants all privileges required to enroll computers and mobile devices.
- **Custom**—Requires you to grant privileges manually.

If there are multiple users that should have the same access level and privileges, you can create a group with the desired access level and privileges and add accounts to it. Members of a group inherit the access level and privileges from the group. Adding an account to multiple groups allows you to grant a user access to multiple sites.

There are two ways to create Jamf Pro user accounts and groups: you can create standard accounts or groups, or you can add them from an LDAP directory service.

Important: It is recommended that you have at least one account that is not from an LDAP directory service in case the connection between the Jamf Pro server and the LDAP server is interrupted.

The Jamf Pro User Accounts and Groups settings also allow you to do the following:

- Configure account preferences for each Jamf Pro user account.
- Configure the password settings in the Password Policy for all standard Jamf Pro user accounts.
- Unlock a Jamf Pro user account that is locked.

Requirements

To add accounts or groups from an LDAP directory service, you need an LDAP server set up in Jamf Pro. (For more information, see “Integrating with LDAP Servers” in the *Jamf Pro Administrator’s Guide*.)

Creating a Jamf Pro User Group

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Jamf Pro User Accounts & Groups** .
5. Click **New** .
6. Do one of the following:

- To create a standard Jamf Pro user group, select **Create Standard Group** and click **Next**.
 - To add a Jamf Pro user group from an LDAP directory service, select **Add LDAP Group** and click **Next**. Then follow the onscreen instructions to search for and add the group.
7. Use the Group pane to configure basic settings for the group.
 8. If you chose “Custom” from the **Privilege Set** pop-up menu, click the **Privileges** tab and select the checkbox for each privilege that you want to grant the group.
 9. Click **Save**.

Creating a Jamf Pro User Account

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Jamf Pro User Accounts & Groups** .
5. Click **New**  **New**.
6. Do one of the following:
 - To create a standard Jamf Pro user account, select **Create Standard Account** and click **Next**.
 - To add a Jamf Pro user account from an LDAP directory service, select **Add LDAP Account** and click **Next**. Then follow the onscreen instructions to search for and add the account.
7. On the Account pane, enter information about the account as needed.
8. Choose an access level from the **Access Level** pop-up menu:
 - To grant full access to Jamf Pro, choose “Full Access”.
 - To grant access to a site, choose “Site Access”.
Note: The “Site Access” option is only displayed if there are sites in Jamf Pro. For more information on adding sites to Jamf Pro, see “Sites” in the *Jamf Pro Administrator's Guide*.
 - To add the account to a standard group, choose “Group Access”.
Note: The “Group Access” option is only displayed if there are standard groups in Jamf Pro. For more information on creating groups, see [Creating a Jamf Pro User Group](#).
9. Do one of the following:
 - If you granted the account full access or site access, choose a privilege set from the **Privilege Set** pop-up menu. Then, if you chose “Custom”, click the **Privileges** tab and select the checkbox for each privilege that you want to grant the account.
 - If you added the account to a group, click the **Group Membership** tab and select the group(s) you want to add the account to.
10. Click **Save**.

Configuring Account Preferences

You can configure Language & Region and Search preferences for each Jamf Pro user account. Language & Region preferences allow you to configure settings such as date format and time zone. Search preferences allow you to configure settings for computer, mobile device, and user searches.

1. Log in to Jamf Pro.
2. At the top of the page, click the account settings  icon and then click **Account Preferences**.
3. Click the **Language & Region** tab and use the pop-up menus to configure language and region preferences.
4. Click the **Search Preferences** tab and use the pop-up menus to configure search preferences.
Note: The default search preference is "Exact Match". For most items, the option can be changed to either "Starts with" or "Contains".
5. Click **Save**.

Configuring the Password Policy

The Password Policy in Jamf Pro allows you to configure the password settings. The Password Policy applies to all standard Jamf Pro user accounts. You can configure the following password settings:

- Number of login attempts allowed before a Jamf Pro user is locked out of the account
- Password length and age
- Password reuse limitations
- Password complexity
- Settings to allow a user to unlock their own account

Note: The settings configured in the Password Policy do not apply to Jamf Pro user accounts added from an LDAP directory service.

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Jamf Pro User Accounts & Groups** .
5. Click **Password Policy**.
6. Click **Edit**.
7. Use the settings on the pane to specify the password settings.
8. Click **Save**.

The settings are applied immediately.

Unlocking a Jamf Pro User Account

A Jamf Pro user could be locked out of their account if they exceed the specified number of allowed login attempts. If the Password Policy is configured to allow the user to unlock their account, the user can reset their password to unlock their account. In this case, an email is immediately sent to the email address associated with the account in Jamf Pro allowing the user to unlock their account by resetting their password. For an email to be sent, an SMTP server must be set up in Jamf Pro. (For more information, see [Integrating with an SMTP Server](#).)

In addition, a Jamf Pro user account that is locked can be manually unlocked from Jamf Pro by another Jamf Pro user with the Administrator privilege set.

The access status of the account is displayed as “Disabled” in Jamf Pro until the account is unlocked.

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Jamf Pro User Accounts & Groups** .
A list of Jamf Pro user accounts and groups is displayed.
5. Click the Jamf Pro user account that has an access status of “Disabled”, which means the account is locked.
6. Click **Edit**.
7. Choose “Enabled” from the **Access Status** pop-up menu to unlock the account.
8. Click **Save**.

The Jamf Pro user account is unlocked immediately.

Related Information

For related information, see the following section in the *Jamf Pro Administrator's Guide*:

"Sites"

Learn about sites and how to add them to Jamf Pro.

Activation Code

The Activation Code settings in Jamf Pro allow you to update the activation code for your license. You can also change the organization name associated with the license and view licensing information.

Updating the Activation Code

Every time you receive a new activation code, it must be updated in Jamf Pro.

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Activation Code** .
5. Click **Edit**.
6. Enter the new activation code.
7. Click **Save**.

Integrating with an SMTP Server

Integrating with an SMTP server allows you to do the following:

- Send email notifications to Jamf Pro users when certain events occur. (For more information, see “Email Notifications” in the *Jamf Pro Administrator’s Guide*.)
- Send enrollment invitations via email.
- Send mass emails to end users.

To integrate with an SMTP server, you need to configure the SMTP Server settings in Jamf Pro.

Configuring the SMTP Server Settings

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **SMTP Server** .
5. Click **Edit**.
6. Configure the settings on the pane.
7. Click **Save**.

Testing the SMTP Server Settings

Once the SMTP Server settings are configured, you can send a test email from Jamf Pro.

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **SMTP Server** .
5. Click **Test**.
6. Enter a test email address and click **Test** again.

A message displays, reporting whether or not the email was sent successfully.

Related Information

For related information, see the following sections in the *Jamf Pro Administrator's Guide*:

- “Email Notifications”
Learn about the different email notifications that can be sent to Jamf Pro users.
- “User-Initiated Enrollment for Computers”
Find out how to send computer enrollment invitations via email.
- “User-Initiated Enrollment for Mobile Devices”
Find out how to send mobile device enrollment invitations via email.
- “Performing Mass Actions for Computers”
Find out how to send a mass email to computer users.
- “Performing Mass Actions for Mobile Devices”
Find out how send a mass email to mobile device users.

Change Management

Change Management allows you to track the changes that happen in Jamf Pro, such as the creation of a Jamf Pro user account. The Change Management settings in Jamf Pro allow you to log those changes to a log file (JAMFChangeManagement.log) on the Jamf Pro host server and/or log the changes to a syslog server.

The Change Management logs can also be viewed in Jamf Pro. The information displayed includes:

- Date/time the change took place
- Username of the administrator who made the change
- Object type (such as a Jamf Pro user account)
- Object name (such as the username of a Jamf Pro user account)
- Action (such as "Created")
- Details about the change

In addition, you can view the changes to a specific object in that object's history. (For more information, see "Viewing the History of a Jamf Pro Object" in the *Jamf Pro Administrator's Guide*.)

Requirements

To log changes to a log file, the account used to run Tomcat must have write permissions for the directory where the JAMFChangeManagement.log file is located.

Configuring the Change Management Settings

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Change Management** .
5. Click **Edit**.
6. Configure the settings on the pane.
7. Click **Save**.

Viewing Change Management Logs in Jamf Pro

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Change Management** .
5. Click **Logs**.
The Change Management logs are displayed on the pane.
6. Do one of the following:
 - To view the object associated with a change, click the object in the Object Name column.
 - To view details about the change, click **Details** in the Details column.

Related Information

For related information, see the following Knowledge Base article:

[Change Management with Jamf Pro: macOS Setup Guide](#)

If you are hosting Jamf Pro on a server with macOS Server installed, learn about setting up the syslogd utility so you can log changes to a syslog server.

Integrating with GSX

Integrating with Apple's Global Service Exchange (GSX) allows you to look up and populate the following purchasing information for computers and mobile devices:

- Purchase date
- Warranty expiration date
- Apple Care ID (warranty reference number)

Note: GSX may not always return complete purchasing information. Only the information found in GSX is returned.

To integrate with GSX, you need to configure the GSX Connection settings in Jamf Pro, which involves entering GSX account information and uploading an Apple certificate.

You can also use Jamf Pro to test the connection and upload a renewed Apple certificate when needed.

Requirements

To configure the GSX Connection settings, you need:

- A GSX account with the "Manager" role, access to Web Services, and access to coverage/warranty information
- An Apple certificate (.pem or .p12)

For instructions on creating a GSX account and obtaining an Apple certificate, see the [Integrating with Apple's Global Service Exchange \(GSX\)](#) Knowledge Base article.

Configuring the GSX Connection Settings

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **Global Management**.
4. Click **GSX Connection** .
5. Click **Edit**.
6. Select **Enable Connection to GSX**.
Note: This and some of the other settings on this pane may already be configured if Jamf Pro was used to generate a CSR.
7. Enter the username and account number for the GSX account.
8. Configure the region and URI settings as needed.
9. Select **Certificate-based Authentication** and click **Upload**.

10. Follow the onscreen instructions to upload the Apple certificate (.pem or .p12).

Testing the GSX Connection

Once the GSX Connection settings are configured, you can test the connection to make sure it works .

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **Global Management**.
4. Click **GSX Connection** .
5. Click **Test**.
6. Click **Test** again.

A message displays, reporting the success or failure of the connection.

Renewing the Apple Certificate

You can use Jamf Pro to upload a renewed Apple certificate without removing the existing certificate so the connection with GSX is not lost. A notification is displayed 31 days prior to the expiration date of the Apple certificate.

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **Global Management**.
4. Click **GSX Connection** .
5. Click **Edit**.
6. Click **Renew**.
7. Follow the onscreen instructions to upload a renewed Apple certificate.

Related Information

For related information, see the following sections in the *Jamf Pro Administrator's Guide*:

- "Performing Mass Actions for Computers"
Find out how to mass look up and populate purchasing information from GSX.
- "Performing Mass Actions for Mobile Devices"
Find out how to mass look up and populate purchasing information from GSX.

- “Viewing and Editing Inventory Information for a Mobile Device”
You can look up and populate purchasing information for a single mobile device by editing the device’s inventory information in Jamf Pro.
- “Viewing and Editing Inventory Information for a Computer”
You can look up and populate purchasing information for a single computer by editing the computer’s inventory information in Jamf Pro.
- “Local Enrollment Using Recon”
Find out how to look up and populate purchasing information when enrolling a computer by running Recon locally.
- “Remote Enrollment Using Recon”
Find out how to look up and populate purchasing information when enrolling a computer by running Recon remotely.

Jamf Pro Summary

The Jamf Pro Summary is a custom report that can be useful for troubleshooting Jamf Pro issues, and for providing information to Jamf for purposes of support or license renewal.

By default, the Jamf Pro Summary includes the following information:

- Number of managed and unmanaged computers
- Number of managed mobile devices
- Operating system on the Jamf Pro host server
- Path to the Jamf Pro web app
- Apache Tomcat version
- Information about the version of Java installed on the Jamf Pro host server
- Information about the MySQL connection and configuration

You can also add information to the Jamf Pro Summary from the following categories as needed:

- Computers
- Mobile Devices
- Users
- System Settings
- Global Management
- Computer Management
- Computer Management–Server Infrastructure
- Computer Management–Management Framework
- Mobile Device Management
- Network Organization
- Database

You can view the Jamf Pro Summary in a browser window or send the Jamf Pro Summary to Jamf.

Requirements

To send the Jamf Pro Summary to Jamf, you need a valid Jamf Nation account.

To create a Jamf Nation account, go to:

<https://www.jamf.com/jamf-nation/users/new>

Viewing the Jamf Pro Summary

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **Jamf Pro Information**.
4. Click **Jamf Pro Summary** .
5. Select the checkboxes next to the items you want to include.
6. Click **Create**.
The Jamf Pro Summary displays in a browser window.
7. Click the **Back** button in the web browser to return to the Jamf Pro Summary pane.

Sending the Jamf Pro Summary to Jamf

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **Jamf Pro Information**.
4. Click **Jamf Pro Summary** .
5. Select the checkboxes next to the items you want to include.
6. Click **Send Summary to Jamf**.
7. Enter your Jamf Nation credentials, and then click **Send**.

The Jamf Pro Summary is sent to Jamf via Jamf Nation.

Related Information

For information about Customer Experience Metrics (CEM), see the following Knowledge Base article:

[Customer Experience Metrics](#)

Learn about Customer Experience Metrics and how to configure the setting in your Jamf Pro environment.

For additional information about Customer Experience Metrics, visit the following webpage:

<https://www.jamf.com/products/jamf-pro/customer-experience-metrics/>

jamf | PRO

Server Infrastructure

About Distribution Points

Distribution points are servers used to host files for distribution to computers and mobile devices. The following types of files can be distributed from a distribution point using Jamf Pro:

- Packages
- Scripts
- In-house apps
- In-house eBooks

Jamf Pro supports three types of distribution points:

- File share distribution points
- A cloud distribution point
- Jamf Distribution Server (JDS) instances

You can use any combination of these types of distribution points.

By default, the first distribution point you add to Jamf Pro is the master distribution point. The master distribution point is used by all other distribution points as the authoritative source for all files during replication. You can change the master distribution point at any time.

When planning your distribution point infrastructure, it is important to understand the differences between each type of distribution point. The following table explains the key differences:

	File Share Distribution Point	Cloud Distribution Point	JDS Instance
Description	Standard server that is configured to be a distribution point	Distribution point that uses one of the following content delivery networks (CDNs) to host files: <ul style="list-style-type: none">▪ Rackspace Cloud Files▪ Amazon Web Services▪ Akamai	Distribution point that is managed by Jamf Pro, similar to a computer or mobile device
Maximum Number per Jamf Pro Instance	Unlimited	One	Unlimited
Server /Platform Requirements	Any server with an Apple Filing Protocol (AFP) or Server Message Block (SMB) share	None	Mac or Linux

	File Share Distribution Point	Cloud Distribution Point	JDS Instance
Protocol	AFP, SMB, HTTP, or HTTPS	HTTPS	HTTPS
Ports	<ul style="list-style-type: none"> ▪ AFP: 548 ▪ SMB: 139 ▪ HTTP: 80 ▪ HTTPS: 443 	443	443
Authentication Options	<ul style="list-style-type: none"> ▪ AFP or SMB: <ul style="list-style-type: none"> ▪ No authentication ▪ Username and password ▪ HTTP or HTTPS: <ul style="list-style-type: none"> ▪ No authentication ▪ Username and password ▪ Certificate-based authentication 	None	<ul style="list-style-type: none"> ▪ No authentication ▪ Certificate-based authentication
Files that Can Be Hosted	<ul style="list-style-type: none"> ▪ Packages ▪ Scripts 	<ul style="list-style-type: none"> ▪ Packages ▪ In-house apps ▪ In-house eBooks <p>Note: If you use the cloud distribution point, scripts are stored in the jamfsoftware database.</p>	<ul style="list-style-type: none"> ▪ Packages ▪ In-house apps ▪ In-house eBooks <p>Note: If you use one or more JDS instances, scripts are stored in the jamfsoftware database.</p>
Parent-Child Capabilities	No	No	Yes
File Replication Method	Replication to file share distribution points must be initiated from Jamf Admin.	Replication to a cloud distribution point must be initiated from Jamf Admin.	Replication to root JDS instances must be initiated from Jamf Admin. Replication to non-root JDS instances happens automatically and immediately.

	File Share Distribution Point	Cloud Distribution Point	JDS Instance
Selective Replication	Not available when replicating to file share distribution points.	Available when replicating to a cloud distribution point if the master distribution point is a JDS instance or file share distribution point. The files for replication must be specified in Jamf Pro and the replication initiated from Jamf Admin.	Not available when replicating to root JDS instances. Available when replicating to non-root JDS instances. The files for replication must be specified in Jamf Pro. The replication from non-root parent to child instances is initiated on check in with Jamf Pro.

Related Information

For related information, see the following sections in this guide:

- [File Share Distribution Points](#)
Find out how to manage file share distribution points in Jamf Pro.
- [Cloud Distribution Point](#)
Find out how to manage the cloud distribution point.
- [Jamf Distribution Server Instances](#)
Find out how to install and manage JDS instances.

File Share Distribution Points

Any server with an AFP or SMB share can be used as a file share distribution point. Before you can use a file share distribution point with Jamf Pro, you must set up the distribution point and add it to Jamf Pro.

For information on setting up a file share distribution point, see the following Knowledge Base article: [Setting Up a File Share Distribution Point](#)

When you add a file share distribution point to Jamf Pro, you can do the following:

- Make it the master distribution point.
- Choose a failover distribution point.
- Configure HTTP downloads.

Adding a File Share Distribution Point

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **Server Infrastructure**.
4. Click **File Share Distribution Points** .
5. Click **New** .
6. Use the General pane to configure basic settings for the distribution point.
7. Click the **File Sharing** tab and enter information about the AFP or SMB share.
8. (Optional) Click the **HTTP** tab and configure HTTP downloads.
9. Click **Save**.

Replicating Files to a File Share Distribution Point

During replication, all files on the master distribution point are replicated to the file share distribution point that you choose.

1. Open Jamf Admin and authenticate to the Jamf Pro server.
2. In the sidebar, select the file share distribution point you want to replicate files to.
3. Click **Replicate**.

Related Information

For related information, see the following section in the *Jamf Pro Administrator's Guide*:

“Network Segments”

You can use network segments to ensure that computers and mobile devices use the closest distribution point by default.

For related information, see the following Knowledge Base articles:

- [Setting Up a File Share Distribution Point on Linux Using Samba](#)
Find out how to use Samba to set up a file share distribution point with an SMB share on a Linux server.
- [Using Apache HTTP Server to Enable HTTP Downloads on a Linux File Share Distribution Point](#)
Find out how to use Apache HTTP Server to enable HTTP downloads on a Linux file share distribution point.
- [Using IIS to Enable HTTP Downloads on a Windows Server 2008 File Share Distribution Point](#)
Find out how to activate Internet Information Services (IIS) and use it to enable HTTP downloads on a Windows Server 2008 file share distribution point.

Cloud Distribution Point

The cloud distribution point uses a content delivery network (CDN) to host packages, in-house apps, and in-house eBooks. Jamf Pro supports the following content delivery services:

- Rackspace Cloud Files
- Amazon S3 or Amazon CloudFront
- Akamai NetStorage
- Jamf Cloud Distribution Service (JCDS)

When you configure the cloud distribution point in Jamf Pro, you can choose to make it the master. You can also choose whether to replicate specific files or the entire contents of the master distribution point if the master is a JDS instance or file share distribution point.

Jamf Pro supports the use of signed URLs created with Amazon CloudFront. It also supports Akamai Remote Authentication. For more information about signed URLs created with CloudFront, see the following website:

<http://docs.aws.amazon.com/AmazonCloudFront/latest/DeveloperGuide/private-content-signed-urls.html>

For more information about Akamai Remote Authentication, contact your Akamai Account Manager.

Requirements

If you plan to use Akamai for your cloud distribution point, Akamai must be configured to use File Transfer Protocol (FTP).

Note: If you have upgraded from Jamf Pro 8.x, you must migrate the scripts and packages on your master distribution point before configuring the cloud distribution point. (For more information, see the [Migrating Packages and Scripts](#) Knowledge Base article.)

Files that are uploaded to a cloud distribution point cannot have filenames that include the following characters:

/ : ? < > \ * | " [] @ ! % ^ #

Configuring the Cloud Distribution Point

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **Server Infrastructure**.
4. Click **Cloud Distribution Point** .
5. Click **Edit**.
6. Choose a content delivery network from the **Content Delivery Network** pop-up menu.
7. Configure the settings on the pane.
8. Click **Save**.

Testing the Cloud Distribution Point

Once the cloud distribution point is configured, you can test the connection to the content delivery network.

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **Server Infrastructure**.
4. Click **Cloud Distribution Point** .
5. Click **Test**.
6. Click **Test** again.

A message displays, reporting the success or failure of the connection.

Replicating Files to the Cloud Distribution Point

During replication, files on the master distribution point are replicated to the cloud distribution point via Jamf Admin. The files that are replicated depend on whether the cloud distribution point is configured to replicate specific files or the entire contents of the master.

1. Open Jamf Admin and authenticate to the Jamf Pro server.
2. In the sidebar, select the cloud distribution point you want to replicate files to.
3. Click **Replicate**.

Related Information

For related information, see the following section in the *Jamf Pro Administrator's Guide*:

“Network Segments”

You can use network segments to ensure that computers and mobile devices use the closest distribution point by default. For related information, see the following Knowledge Base article:

[Information Required to Configure a Cloud Distribution Point in Jamf Pro](#)

Learn about the information that must be obtained from your cloud services provider to configure the cloud distribution point in Jamf Pro.

For more information about content delivery services, visit the following websites:

- Rackspace Cloud Files
<http://www.rackspace.com/cloud/files/>
- Amazon S3
<http://aws.amazon.com/s3/>
- Amazon CloudFront
<http://aws.amazon.com/cloudfront/>
- Akamai NetStorage
<http://www.akamai.com/html/solutions/netstorage.html>
- Jamf Cloud Distribution Service
<http://www.jamfsoftware.com/products/jamf-cloud/>

Jamf Distribution Server Instances

To manage JDS instances in Jamf Pro, you need a valid SSL certificate on the Jamf Pro host server. (For more information, see [SSL Certificate](#).)

Note: If you have upgraded from Jamf Pro 8.x, you must migrate the scripts and packages on your master distribution point before configuring JDS instances. (For more information, see the [Migrating Packages and Scripts](#) Knowledge Base article.)

Configuring a JDS Instance

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **Server Infrastructure**.
4. Click **JDS Instances** .
5. Click the JDS instance you want to configure.
6. Click **Edit**.
7. Use the General pane to configure basic settings for the JDS instance.
8. Click the **Distribution Point** tab and configure distribution settings.
9. Click **Save**.

Replicating Files to the Root JDS Instance

During replication, all files on the master distribution point are replicated to the root JDS instance. Then, files are replicated to child JDS instances from their non-root parent instances on check in with Jamf Pro. The files that are replicated to non-root JDS instances depend on whether each instance is configured to replicate specific files or the entire contents of their parent JDS instance.

1. Open Jamf Admin and authenticate to the Jamf Pro server.
2. In the sidebar, select the root JDS instance.
3. Click **Replicate**.

Viewing the Progress of File Replication

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **Server Infrastructure**.

4. Click **JDS Instances**  .
5. Click **Grid View**  at the top of the list.

The progress of file replication for each JDS instance is displayed. If your master distribution point is a JDS instance, it is marked with two asterisks (**). If your master distribution point is a different type of distribution point, the root instance is marked with a single asterisk (*).

Viewing Inventory Information for a JDS Instance

Jamf Pro displays the following inventory information for each JDS instance:

- Whether or not it is the master distribution point
- Whether or not it is the root instance
- Hostname
- URL
- Reported IP address
- jamfds binary version
- Operating system
- Operating system version
- Total memory
- Available memory
- Hard drive size
- Hard drive used space

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings**  .
3. Click **Server Infrastructure**.
4. Click **JDS Instances**  .
5. Click the JDS instance you want to view inventory information for.

Related Information

For related information, see the following section in the *Jamf Pro Administrator's Guide*:

“Network Segments”

You can use network segments to ensure that computers and mobile devices use the closest distribution point by default.

For related information, see the following Knowledge Base articles:

- [Components Installed on JDS Instances](#)
Find out what items are installed on JDS instances.
- [Changing JDS Hierarchy](#)
Learn about the implications of changing your JDS hierarchy.
- [Uninstalling a JDS Instance](#)
Find out how to uninstall a JDS instance.

Jamf Infrastructure Manager Instances

A Jamf Infrastructure Manager instance is a service that is managed by Jamf Pro. It can be used to host the following:

- **LDAP Proxy**—This allows traffic to pass securely between Jamf Pro and an LDAP directory service. The Infrastructure Manager and the LDAP Proxy typically reside within the DMZ. The LDAP Proxy requires integration with an LDAP directory service. For more information, see "LDAP Proxy" in the *Jamf Pro Administrator's Guide*.
- **Healthcare Listener**—This allows traffic to pass securely from a healthcare management system to Jamf Pro. For more information, see "Healthcare Listener" in the *Jamf Pro Administrator's Guide*.

When you install an instance of the Infrastructure Manager, Jamf Pro allows you to enable the LDAP Proxy or the Healthcare Listener. Infrastructure Manager instances can be installed on Linux and Windows. For more information, see the [Jamf Infrastructure Manager Installation Guide](#).

Viewing Inventory Information for a Jamf Infrastructure Manager Instance

Jamf Pro displays the following inventory information for each Infrastructure Manager instance:

- Last Check-in
- IP Address at Last Check-in
- Operating System
- Operating System Version

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **Computer Management**.
4. In the "Computer Management–Server Infrastructure" section, click **Infrastructure Managers** . A list of Infrastructure Manager instances is displayed along with the services that are installed on each instance.
5. Click the Infrastructure Manager instance you want to view inventory information for.

Further Considerations

- When editing an Infrastructure Manager instance, only the display name and recurring check-in frequency can be changed.
Note: The default check-in frequency at which the Infrastructure Manager instance checks in with Jamf Pro is 30 seconds.

- An Infrastructure Manager instance cannot be deleted if there are dependencies for the Infrastructure Manager. For example, an Infrastructure Manager cannot be deleted if there is an LDAP Proxy hosted on it. To delete the Infrastructure Manager, you must first disable the LDAP Proxy.
- If a Healthcare Listener is hosted on the Infrastructure Manager, the Healthcare Listener is deleted when the Infrastructure Manager is deleted.

Related Information

For related information, see the following section in the *Jamf Pro Administrator's Guide*:

"Email Notifications"

Learn how to enable an email notification in the event that an Infrastructure Manager instance does not check in with Jamf Pro.

jamf | PRO

Advanced Configuration

SSL Certificate

Jamf Pro requires a valid SSL certificate to ensure that computers and mobile devices communicate with the Jamf Pro server and not an imposter server.

The Apache Tomcat settings in Jamf Pro allow you to create an SSL certificate from the CA that is built into Jamf Pro. You can also upload the certificate keystore for an SSL certificate that was obtained from an internal certificate authority (CA) or a trusted third-party vendor.

Note: If your environment is hosted in Jamf Cloud, the Apache Tomcat settings are managed by Jamf Cloud and are not accessible.

Requirements

To create or upload an SSL certificate, Jamf Pro must be installed as the “ROOT” web app, and the user running the Tomcat process must have read/write access to Tomcat’s `server.xml` file.

Creating or Uploading an SSL Certificate

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Apache Tomcat Settings** .
5. Click **Edit**.
6. Select **Change the SSL certificate used for HTTPS** and click **Next**.
7. Follow the onscreen instructions to upload or create an SSL certificate.
8. Restart Tomcat for the changes to take effect.
For instructions on how to restart Tomcat, see the following Knowledge Base article: [Starting and Stopping Tomcat](#)

Related Information

For related information, see the following Knowledge Base article:

[Using OpenSSL to Create a Certificate Keystore for Tomcat](#)

Find out how to use OpenSSL to create a certificate keystore that you can upload to Jamf Pro.

Configuring Tomcat to Work with a Load Balancer

When Jamf Pro is behind a load balancer, you must configure the remote IP valve, proxy port, and scheme in Tomcat's `server.xml` file. The Load Balancing settings in Jamf Pro allow you to configure these settings without having to edit the `server.xml` file manually.

Requirements

To configure Load Balancing settings using Jamf Pro, Jamf Pro must be installed as the "ROOT" web app, and the user running the Tomcat process must have read/write access to Tomcat's `server.xml` file.

Configuring Load Balancing Settings

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Apache Tomcat Settings** .
5. Click **Edit**.
6. Select **Configure Tomcat for working behind a load balancer** and click **Next**.
7. Follow the onscreen instructions to configure the Load Balancing settings.
8. Restart Tomcat for the changes to take effect.
For instructions on how to restart Tomcat, see the following Knowledge Base article: [Starting and Stopping Tomcat](#)

Tomcat Thread Pool Settings

Configuring the Tomcat Thread Pool settings using Jamf Pro allows you to make modifications to Tomcat's `server.xml` file without having to edit it manually.

Requirements

To configure Tomcat Thread Pool settings using Jamf Pro, Jamf Pro must be installed as the "ROOT" web app, and the user running the Tomcat process must have read/write access to Tomcat's `server.xml` file.

Configuring Tomcat Thread Pool Settings

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Apache Tomcat Settings** .
5. Click **Edit**.
6. Select **Update the settings for Tomcat's thread pool** and click **Next**.
7. Follow the onscreen instructions to configure the Thread Pool settings.
8. Restart Tomcat for the changes to take effect.
For instructions on how to restart Tomcat, see the following Knowledge Base article: [Starting and Stopping Tomcat](#)

Jamf Pro Web App Memory

Jamf Pro allows you to view the amount of memory being used by the web app. If you need to change the amount of memory allocated to the web app, you can use the Jamf Pro database utility (formerly the JSS database utility) to do so.

Viewing Memory Usage


1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **Jamf Pro Information**.
4. Click **Memory Usage** .
A pie chart of used and available memory is displayed.

Configuring Web App Memory Using the GUI

1. Open the Jamf Pro database utility on the Jamf Pro host server by executing:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar
```

2. If prompted, enter the password for your account and then press the Return key.
3. If the Jamf Pro database utility is unable to locate the MySQL binary, you are prompted to enter the path. Click **Continue** and enter the full path to the binary.
4. From the menu bar, choose **Utilities > Change Tomcat settings**.
5. Use the Maximum Memory and Minimum Memory sliders to configure the amount of memory allocated to the web app.



6. Click **Apply Settings**.
7. When prompted to restart Tomcat, click **Yes**.

Configuring Web App Memory Using the Command Line

1. Open the file that contains the Tomcat memory settings.

- If you used the Jamf Pro Installer to install Jamf Pro, execute:

```
sudo nano /usr/local/jss/tomcat/bin/setenv.sh
```

- If you did not use the Jamf Pro Installer to install Jamf Pro, create the `setenv.sh` file in the following location:

```
/usr/local/jss/tomcat/bin/
```

2. Append a custom `JAVA_OPTS` environment variable to the bottom of the `setenv.sh` file to configure the amount of memory allocated to the web app. For example, to allocate 1 GB of RAM, the variable should look something like this:

```
JAVA_OPTS=" -Xmx1024M -XX:MaxPermSize=256M"
```

Note: Custom settings will persist after performing an upgrade.

3. Save and close the file by pressing Control-O, and then Control-X.

4. Restart Tomcat for the change to take effect.

For instructions on how to restart Tomcat, see the following Knowledge Base article:

[Starting and Stopping Tomcat](#)

Viewing the Status of Database Tables

MySQL database tables can become corrupt if the database was not shut down properly or if the Jamf Pro host server is too slow to manage the number of computers in your organization. You can view the status of database tables right from Jamf Pro.

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **Jamf Pro Information**.
4. Click **Database Table Summary** .

Clustering

A clustered environment is one that has multiple instances of the Jamf Pro web app pointing to the same database. Clustering is useful in large environments that require multiple web apps, or environments with a web app in the DMZ.

When setting up a clustered environment, it is recommended that you configure the Clustering settings in Jamf Pro using the web app that you plan to make the master, and then install other Jamf Pro web apps that point to the same database. However, if you already have multiple Jamf Pro web apps installed and pointed to the same database, you can configure the Clustering settings in Jamf Pro after the fact. (For more information on setting up a clustered environment, contact your Jamf account representative.)

The Clustering settings in Jamf Pro allow you to configure the frequency at which clustered web apps are synced with the database, and specify which web app should function as the master.

The master web app handles tasks such as upgrading the database schema and flushing logs from the database.

Jamf Pro also allows you to view a list of web apps that are pointed to the same database and information about them.

Requirements

To cluster web apps that are not in the DMZ, you need a load balancer with the address of the Jamf Pro server (formerly the Jamf Software Server). For example:

`https://jss.mycompany.com:8443/`

The load balancer should route traffic to the servers running the web app.

Configuring Clustering Settings

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Clustering** .
5. Click **Edit**.
6. Configure the settings on the pane.
To specify which web app should function as the master, select the **Master** option for the web app.
7. Click **Save**.

8. If you already have multiple Jamf Pro web apps pointed to the same database, restart Tomcat on any of the web apps for the changes to take effect.

For instructions on how to restart Tomcat, see the following Knowledge Base article:

[Starting and Stopping Tomcat](#)

Related Information

For related information, see the following Knowledge Base articles:

[Caching Configuration](#)

Find out how to configure distributed caching for clustered Jamf Pro environments.

[Installing a Jamf Pro Web App in the DMZ](#)

Find out how to install a web app in the DMZ, and learn when in the process you should configure the Clustering settings in Jamf Pro.

Limited Access Settings

If you have a clustered environment, the Limited Access settings in Jamf Pro allow you to disable the Jamf Pro interface and limit the types of devices that can communicate with Jamf Pro. This is most commonly used if you have a web app in the DMZ.

For each Jamf Pro web app, you can choose one of the following Limited Access settings:

- Full Access
- Computer Access Only
- Mobile Device Access Only
- Computer and Mobile Device Access

Choosing anything other than “Full Access” disables the Jamf Pro interface.

Configuring the Limited Access Settings

1. Log in to any of the Jamf Pro web apps.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Limited Access** .
5. Select a setting for each Jamf Pro web app as needed.
6. Click **Save**.

Backing Up the Database

Using the Jamf Pro database utility (formerly the JSS database utility), you can create database backups as needed or schedule database backups to be created automatically on a schedule. The time it takes to create a backup depends on the size of the database.


When you schedule database backups, you can also automate the deletion of scheduled backups that are older than a certain number of days.

Creating Database Backups Using the GUI

1. Open the Jamf Pro database utility by executing:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar
```

2. If prompted, enter the password for your account and press the Return key.
3. If the Jamf Pro database utility is unable to locate the MySQL binary, you are prompted to enter the path. Click **Continue** and enter the full path to the binary.
4. If the Database Connection Setup pane appears, configure the settings to match your database configuration and click **Apply Settings**.
5. Click **Save Backup Now**.



6. Select the location where you want to save the backup and click **Choose**.

The Jamf Pro database utility creates the backup and saves it as a .sql.gz file.

Creating Database Backups Using the Command Line

1. Execute the following command:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar backup -
saveBackupTo <path>
```

For example:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar backup -
saveBackupTo /home/username/backups/
```

2. If prompted, enter the password for your account and press the Return key.
3. If prompted, configure the database configuration settings to match your own by executing:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar backup -
saveBackupTo <path> -server <database server address> -port
<database port> -database <database name> -user <database user> -
pass
```

For example:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar backup -
saveBackupTo /home/username/backups/ -server localhost -port 3306 -
database jamfsoftware -user jss -pass
```

The Jamf Pro database utility creates the backup and saves it as a .sql.gz file.

To access command-line help for the backup verb, execute:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar help backup
```


Scheduling Database Backups Using the GUI

1. Open the Jamf Pro database utility by executing:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar
```

2. If prompted, enter the password for your account and press the Return key.
3. If the Jamf Pro database utility is unable to locate the MySQL binary, you are prompted to enter the path. Click **Continue** and enter the full path to the binary.

4. If the Database Connection Setup pane appears, configure the settings to match your database configuration and click **Apply Settings**.
5. Select the **Schedule automatic backups for** checkbox and choose the hour of the day that you want backups to occur.
6. To save the backups in a custom location, click the **Change** button and select a new location.



7. To automate the deletion of scheduled backups, select the **Delete backups older than** checkbox, and choose the number of days after which backups should be deleted.

The Jamf Pro database utility creates daily backups at the hour you specified. It also deletes scheduled backups older than the number of days you specified.

Scheduling Database Backups Using the Command Line

1. Execute a command similar to the following:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar schedule -
hour <number between 0 and 23> -scheduledBackupPath <path> -
deleteBackupsOlderThanDays <number greater than 0>
```

For example:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar schedule -
hour 3 -scheduledBackupPath /home/username/backups/ -
deleteBackupsOlderThanDays 7
```

2. If prompted, enter the password for your account and press the Return key.

3. If prompted, configure the database configuration settings to match your own by executing a command similar to the following:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar schedule -
hour <number between 0 and 23> -scheduledBackupPath <path> -
deleteBackupsOlderThanDays <number greater than 0> -server
<database server address> -port <database port> -database <database
name> -user <database user> -pass
```

For example:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar schedule -
hour 3 -scheduledBackupPath /home/username/backups/ -
deleteBackupsOlderThanDays 7 -server localhost -port 3306 -database
jamfsoftware -user jss -pass
```

The Jamf Pro database utility creates daily backups at the hour you specified. It also deletes scheduled backups older than the number of days you specified.

To access command-line help for the `schedule` verb, execute:


```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar help schedule
```

Stopping Scheduled Database Backups Using the GUI

1. Open the Jamf Pro database utility by executing:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar
```

2. If prompted, enter the password for your account and press the Return key.
3. If the Jamf Pro database utility is unable to locate the MySQL binary, you are prompted to enter the path. Click **Continue** and enter the full path to the binary.
4. If the Database Connection Setup pane appears, configure the settings to match your database configuration and click **Apply Settings**.
5. Deselect the **Schedule automatic backups for** checkbox.



The Jamf Pro database utility stops creating scheduled backups immediately.

Stopping Scheduled Database Backups Using the Command Line

Execute the following command:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar unschedule
```

The Jamf Pro database utility stops creating scheduled backups immediately.

To access command-line help for the `unschedule` verb, execute:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar help  
unschedule
```

Related Information

For related information, see the following section in this guide:

[Restoring Database Backups](#)

Find out how to restore database backups.

Restoring Database Backups


If you need to revert to an earlier version of your database, you can restore a database backup using the Jamf Pro database utility (formerly the JSS database utility).

Restoring a Database Backup Using the GUI

1. Open the Jamf Pro database utility by executing:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar
```

2. If prompted, enter the password for your account and then press the Return key.
3. If the Jamf Pro database utility is unable to locate the MySQL binary, you are prompted to enter the path. Click **Continue** and enter the location of the binary.
4. If the Database Connection Setup pane appears, edit the settings to match your database configuration and click **Apply Settings**.
5. Click **Restore Backup Now**.



6. Select the backup that you want to restore (.sql or .sql.gz) and click **Choose**.
7. When prompted to restart Tomcat, click **Yes**.

The Jamf Pro database utility restarts Tomcat and replaces the current database with the one that you restored.

Restoring a Database Backup Using the Command Line

1. Execute a command similar to the following:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar restore -file  
<filename>
```

For example:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar restore -file  
backup.sql.gz
```

2. If prompted, enter the password for your account and then press the Return key.
3. If prompted, edit the database configuration settings to match your own by executing a command similar to the following:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar restore -file  
<filename> -server <database server address> -port <database port> -  
database <database name> -user <database user> -pass
```

For example:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar restore -file  
backup.sql.gz -server localhost -port 3306 -database jamfsoftware -  
user jss -pass
```

4. Restart Tomcat by executing:

```
sudo /etc/init.d/jamf.tomcat7 restart
```

The Jamf Pro database utility replaces the current database with the one that you restored.

To access command-line help for the `restore` verb, execute:

```
sudo java -jar /usr/local/jss/bin/JSSDatabaseUtil.jar help restore
```

Flushing Logs

Flushing logs reduces the size of the database and can speed up searches. You can flush the following types of logs:

- Application Usage logs
- Computer Usage logs
- Policy logs
- Jamf Remote logs
- Screen sharing logs
- Jamf Imaging logs
- Computer and mobile device management history
- JDS management history
- Computer inventory reports (computer inventory information from past inventory submissions)
- Mobile device inventory reports (mobile device inventory information from past inventory submissions)
- Jamf Pro access logs
- Change Management logs
- Event logs

You can schedule log flushing to take place daily, or you can manually flush logs as needed. You can also choose to flush logs that are older than a certain number of days, weeks, or months.

For information on the types of data flushed with each log and the database tables affected, see the following Knowledge Base article:

[Data and Tables Affected by Log Flushing](#)

Scheduling Log Flushing

1. Log in to Jamf Pro.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Log Flushing** .
5. Click **Edit**.
6. Use the pop-up menus to choose the number of days, weeks, or months after which each type of log should be flushed.

7. Choose a time of day from the **Time to Flush Logs Each Day** pop-up menu.
8. Click **Save**.

Manually Flushing Logs

1. Log in to any of the Jamf Pro web apps.
2. In the top-right corner of the page, click **Settings** .
3. Click **System Settings**.
4. Click **Log Flushing** .
5. Click **Flush Manually**.
6. Select the checkbox for each type of log you want to flush.
7. From the **Flush Logs Older Than** pop-up menu, choose the number of days, weeks, or months after which logs should be flushed.
8. Click **Flush**.

A message displays, reporting the success or failure of the flush.

Related Information

For related information, see the following sections in the *Jamf Pro Administrator's Guide*:

- "Viewing and Flushing Policy Logs for a Computer"
Find out how to view and flush policy logs for a computer.
- "Viewing and Flushing Logs for a Policy"
Find out how to view and flush logs for a policy.
- "Viewing the History for a Computer"
Find out how to view the logs and the management history for a computer.
- "Viewing the Management History for a Mobile Device"
Find out how to view the management history for a mobile device.

Migrating to Another Server

1. Back up the existing Jamf Pro database using the Jamf Pro database utility (formerly the JSS database utility).
For more information, see [Backing Up the Database](#).
2. Ensure that the new server meets the requirements for the Jamf Pro Installer, and then follow the instructions in [Installing Jamf Pro](#) to install the required software (if needed) and create the Jamf Pro database.
3. Copy the Jamf Pro Installer to the new server.
4. Install Jamf Pro by launching the installer and following the onscreen instructions.
For more information, see [Installing Jamf Pro](#).
5. Copy the database backup to the new server, and then use the Jamf Pro database utility to restore the backup.
For more information, see [Restoring Database Backups](#).
6. Re-upload or create the SSL certificate.
For more information, see [SSL Certificate](#).
7. Update the DNS entry to point to the new server's IP address.
Note: If you can't change the DNS entry, you must change the Jamf Pro URL and re-enroll all mobile devices and computers.